

QWERTY Keyboard keys		
Key Name	Value	Description
KEYCODE_0	7 (0x07)	0
KEYCODE_1	8 (0x08)	1
KEYCODE_2	9 (0x09)	2
KEYCODE_3	10 (0x0A)	3
KEYCODE_4	11 (0x0B)	4
KEYCODE_5	12 (0x0C)	5
KEYCODE_6	13 (0x0D)	6
KEYCODE_7	14 (0x0E)	7
KEYCODE_8	15 (0x0F)	8
KEYCODE_9	16 (0x10)	9
KEYCODE_STAR	17 (0x11)	*
KEYCODE_POUND	18 (0x12)	#
KEYCODE_A	29 (0x1D)	A
KEYCODE_B	30 (0x1E)	B
KEYCODE_C	31 (0x1F)	C
KEYCODE_D	32 (0x20)	D
KEYCODE_E	33 (0x21)	E
KEYCODE_F	34 (0x22)	F
KEYCODE_G	35 (0x23)	G
KEYCODE_H	36 (0x24)	H
KEYCODE_I	37 (0x25)	I
KEYCODE_J	38 (0x26)	J
KEYCODE_K	39 (0x27)	K
KEYCODE_L	40 (0x28)	L
KEYCODE_M	41 (0x29)	M
KEYCODE_N	42 (0x2A)	N
KEYCODE_O	43 (0x2B)	O
KEYCODE_P	44 (0x2C)	P
KEYCODE_Q	45 (0x2D)	Q
KEYCODE_R	46 (0x2E)	R
KEYCODE_S	47 (0x2F)	S
KEYCODE_T	48 (0x30)	T
KEYCODE_U	49 (0x31)	U
KEYCODE_V	50 (0x32)	V
KEYCODE_W	51 (0x33)	W
KEYCODE_X	52 (0x34)	X
KEYCODE_Y	53 (0x35)	Y

QWERTY Keyboard keys (cont)		
KEYCODE_Z	54 (0x36)	Z
KEYCODE_COMMA	55 (0x37)	, (comma)
KEYCODE_PERIOD	56 (0x38)	. (Period)
KEYCODE_ALT_LEFT	57 (0x39)	Left Alt modifier key
KEYCODE_ALT_RIGHT	58 (0x3A)	Right Alt modifier key
KEYCODE_SHIFT_LEFT	59 (0x3B)	Left Shift modifier key
KEYCODE_SHIFT_RIGHT	60 (0x3C)	Right Shift modifier key
KEYCODE_TAB	61 (0x3D)	Horizontal Tab
KEYCODE_SPACE	62 (0x3E)	Space
KEYCODE_ENTER	66 (0x42)	Enter
KEYCODE_DEL	67 (0x43)	Backspace
KEYCODE_GRAVE	68 (0x44)	` (Backtick)
KEYCODE_MINUS	69 (0x45)	- (Minus)
KEYCODE_EQUALS	70 (0x46)	= (Equals)
KEYCODE_LEFT_BRACKET	71 (0x47)	[
KEYCODE_RIGHT_B-RACKET	72 (0x48)	]
KEYCODE_BACKSLASH	73 (0x49)	\ (Back slash)
KEYCODE_SEMICOLON	74 (0x4A)	; (Semicolon)
KEYCODE_APOSTROPHE	75 (0x4B)	" (apostrophe)
KEYCODE_SLASH	76 (0x4C)	/ (Forward slash)
KEYCODE_AT	77 (0x4D)	@
KEYCODE_PLUS	81 (0x51)	+ (Plus)
KEYCODE_FORWARD_DEL	112 (0x70)	Delete

Physical Buttons		
KEYCODE_SOFT_RIGHT	2 (0x02)	Soft Right key
KEYCODE_HOME	3 (0x03)	Home key
KEYCODE_CALL	5 (0x05)	Call key
KEYCODE_ENDCALL	6 (0x06)	End Call key
KEYCODE_VOLUME_UP	24 (0x18)	Volume Up
KEYCODE_VOLUME_DOWN	25 (0x19)	Volume Down
KEYCODE_POWER	26 (0x1A)	Power key
KEYCODE_CAMERA	27 (0x1B)	Camera key
KEYCODE_CLEAR	28 (0x1C)	Clear key

These are the physical buttons on the device



### Media keys

KEYCODE_MEDIA_PLAY_PAUSE	085 (0x55)	Play/Pause media
KEYCODE_MEDIA_STOP	086 (0x56)	Stop media
KEYCODE_MEDIA_NEXT	087 (0x57)	Play Next media
KEYCODE_MEDIA_PREVIOUS	088 (0x58)	Play Previous media
KEYCODE_MEDIA_REWIND	089 (0x59)	Rewind media
KEYCODE_MEDIA_FAST_FORWARD	090 (0x5a)	Fast Forward media
KEYCODE_MUTE	091 (0x5b)	Mutes the microphone
KEYCODE_MEDIA_PLAY	126 (0x7e)	Play media
KEYCODE_MEDIA_PAUSE	127 (0x7f)	Pause media
KEYCODE_MEDIA_CLOSE	128 (0x80)	Close media (CD)
KEYCODE_MEDIA_EJECT	129 (0x81)	Eject media (CD)
KEYCODE_MEDIA_RECORD	130 (0x82)	Record media
KEYCODE_MEDIA_SKIP_FORWARD	272 (0x0110)	Skip forward media
KEYCODE_MEDIA_SKIP_BACKWARD	273 (0x0111)	Skip backward media
KEYCODE_MEDIA_STEP_FORWARD	274 (0x0112)	Step forward media
KEYCODE_MEDIA_STEP_BACKWARD	275 (0x0113)	Step backward media

### Game Controller Keys

KEYCODE_BUTTON_A	96 (0x60)	Button-A
KEYCODE_BUTTON_B	97 (0x61)	Button-B
KEYCODE_BUTTON_C	98 (0x62)	Button-C
KEYCODE_BUTTON_X	99 (0x63)	Button-X
KEYCODE_BUTTON_Y	100 (0x64)	Button-Y
KEYCODE_BUTTON_Z	101 (0x65)	Button-Z
KEYCODE_BUTTON_L1	102 (0x66)	Top Left Trigger Button-1
KEYCODE_BUTTON_R1	103 (0x67)	Top Right Trigger Button-1
KEYCODE_BUTTON_L2	104 (0x68)	Top Left Trigger Button-2

### Game Controller Keys (cont)

KEYCODE_BUTTON_R2	105 (0x69)	Top Right Trigger Button-2
KEYCODE_BUTTON_THUMBL	106 (0x6a)	Left Thumb Button
KEYCODE_BUTTON_THUMBR	107 (0x6b)	Right Thumb Button
KEYCODE_BUTTON_START	108 (0x6c)	Start Button
KEYCODE_BUTTON_SELECT	109 (0x6d)	Select Button
KEYCODE_BUTTON_ON_MODE	110 (0x6e)	Mode Button

### Number Pad Keys

KEYCODE_NUM	78 (0x4e)	Used to enter numeric symbols.
KEYCODE_NUM_LOCK	143 (0x8f)	Num Lock key.
KEYCODE_NUMPAD_0	144 (0x90)	Numeric keypad '0' key.
KEYCODE_NUMPAD_1	145 (0x91)	Numeric keypad '1' key.
KEYCODE_NUMPAD_2	146 (0x92)	Numeric keypad '2' key.
KEYCODE_NUMPAD_3	147 (0x93)	Numeric keypad '3' key.
KEYCODE_NUMPAD_4	148 (0x94)	Numeric keypad '4' key.
KEYCODE_NUMPAD_5	149 (0x95)	Numeric keypad '5' key.
KEYCODE_NUMPAD_6	150 (0x96)	Numeric keypad '6' key.
KEYCODE_NUMPAD_7	151 (0x97)	Numeric keypad '7' key.
KEYCODE_NUMPAD_8	152 (0x98)	Numeric keypad '8' key.
KEYCODE_NUMPAD_9	153 (0x99)	Numeric keypad '9' key.

### Number Pad Keys (cont)

KEYCODE_NUMPAD_DIVIDE	154 (0x9a)	Numeric keypad '/' key.
KEYCODE_NUMPAD_MULTIPLY	155 (0x9b)	Numeric keypad '*' key.
KEYCODE_NUMPAD_SUBTRACT	156 (0x9c)	Numeric keypad '-' key.
KEYCODE_NUMPAD_ADD	157 (0x9d)	Numeric keypad '+' key.
KEYCODE_NUMPAD_DOT	158 (0x9e)	Numeric keypad '.' key.
KEYCODE_NUMPAD_COMMA	159 (0x9f)	Numeric keypad ',' key.
KEYCODE_NUMPAD_ENTER	160 (0xa0)	Numeric keypad Enter key.
KEYCODE_NUMPAD_EQUALS	161 (0xa1)	Numeric keypad '=' key.
KEYCODE_NUMPAD_LEFT_PAREN	162 (0xa2)	Numeric keypad '(' key.
KEYCODE_NUMPAD_RIGHT_PAREN	163 (0xa3)	Numeric keypad ')' key.



By **nandu** (divyanand)  
[cheatography.com/divyanand/](https://cheatography.com/divyanand/)

Published 13th April, 2021.  
Last updated 13th April, 2021.  
Page 3 of 3.

Sponsored by **Readable.com**  
Measure your website readability!  
<https://readable.com>