

General syntax

!	Alt
^	Ctrl
#	Win , the <i>left</i> one
+	Shift

Layout management

#Tab	Set the previous layout
#f	Sets the 3rd layout
#m	Sets the 2nd layout
#t	Sets the 1st layout
#Left	Reduce the size of the master area in the active view
#Right	Increase the size of the master area in the active view
#^t	Rotate the layout axis
#^Enter	Mirror the layout axis
#^Tab	Rotate the master axis
#^+Tab	Rotate the stack axis
#^Up	Increment the master Y dimension, <i>only tile layout</i>
#^Down	Decrement the master Y dimension, <i>only tile layout</i>
#^Left	Decrement the master X dimension, <i>only tile layout</i>
#^Right	Increment the master X dimension, <i>only tile layout</i>
#+Left	Decrease the gap between windows, <i>in monacle and tile layout</i>
#+Right	Increase the gap between windows, <i>in monacle and tile layout</i>

View / Tag management

#+n	Toggle the view margin
#Backsp ace	Activate the previously activated view
#+0	Tag the active window with all tags
#<n>	Activate the nth view
#+<n>	Tag the active window with the nth tag
#^<n>	Toggle the nth tag for the active window

Window management


#Down	Focus the next window in the active view
#Up	Focus the previous window in the active view
#+Down	Move the active window to the next position in the window list of the view
#+Up	Move the active window to the previous position in the window list of the view
#c	Close the active window
#+d	Toggle visibility of the title bar of the focused window
#+f	Toggle the floating status of the active window
#^m	Minimize the active windows, <i>implicitly makes the window floating</i>
#+m	Move the active window by key, <i>only floating windows</i>
#+s	Resize the active window by key, <i>only floating windows</i>

Window management (cont)

#+x	Expand the active window to the size of the work area
#i	<i>Get information</i> about the active window
#+i	<i>Get a window list*</i> for the active view
!Down	Move the active window to the next area
!Up	Move the active window to the previous area
!+Enter	Expand the active window to the size of the work area , <i>only floating windows</i>
+<n>	Move the active window to the nth area
!Backspace	Toggle the stack area of the layout. If disabled, the master area takes up the whole view

Monitor management

#.	Activate the next monitor
#,	Activate the previous monitor
#+. .	Move the active window to the next monitor
#+,	Move the active window to the previous monitor
#^+. .	Move all windows to the next monitor
#^+,	Move all windows to the previous monitor



By [gamer204](#)
cheatography.com/gamer204/

Published 6th July, 2015.
Last updated 8th July, 2015.
Page 1 of 2.

Sponsored by CrosswordCheats.com
Learn to solve cryptic crosswords!
<http://crosswordcheats.com>

GUI Management

- #+Space **Toggle** visibility of the **bug.n status bar**
- #Space **Toggle** visibility of the **Windows task bar**
- #y **Toggle** the overflow window of the **notify icons**
- !+y **Indicate the areas** of the tile layout

Administration

- #^e **Open the configuration file** in Notepad
- #^s **Save the current state** of monitors, views, layouts to the configuration file
- #^r **Reload bug.n**
- #^q **Quit bug.n**

Window debugging

- `#^i **Dump window information** on the windows of the active view to the log
- `#+^i **Dump window information on the contents of the managed window list** to the log
- #^h Print a **description of the formatting (column headings)** used in the previous two log messages to the log
- #^d **Decrement** the debug **log level**
- #^+d **Increment** the debug **log level**



By [gamer204](#)
cheatography.com/gamer204/

Published 6th July, 2015.
Last updated 8th July, 2015.
Page 2 of 2.

Sponsored by [CrosswordCheats.com](#)
Learn to solve cryptic crosswords!
<http://crosswordcheats.com>