

Basic Navigation

hjk ^l	Move cursor down, up, right or left.
^	Go up to row 0 of the current column.
#	Go down to the last valid row of the current column.
0	Go left to column A in the current row.
\$	Go right to the last valid column of the current row.
b/w	Go back/forward to the previous valid cell.
gg/G	Go to the first/last cell of sheet.
g1	Go to the last (previously occupied) cell position
gab24	Go to cell AB24.
'{aZ}	Go to the cell/range marked previously with the char.

Insert Mode

=	Enter a numeric constant or expression.
<	Enter a left justified string or string expression.
\	Enter a centered label.
>	Enter a right justified string or string expression.
<bs>	Delete the character after or before the cursor.
<tab>	Return to Edit mode from Insert mode.
^v	Enter Visual mode.

Commands for handling cell content

x	Delete the current selected cell or range and save its content in the yankbuffer.
{ }	Align the content of a cell to the left/right/center.
f [jk]	Decrement/Increment decimal precision.
f [hl]	Decrement/Increment column width.
i [rc]	Insert a row/column.
o [rc]	Insert after the current row/column.
s [hjkl]	Shifts the current cell or range left/down/up/right.
yy	Yank the selected cell.
y	If a range is selected, yank the range.
y [rc]	Yank current row/column.
p	Paste the previously yanked cell or range.
d [rc]	Delete the current row/column.
-/+	Decrease/Increase a numeric value of the cell or range.

Commands for handling cell content (cont)

u/^r	UNDO/REDO last change
.	Repeat the last normal mode command.
aa	Auto-resize the selected column(s) to accommodate the widest cells

Scroll Navigation

^ [fb]	Scrolls down/up full screen.
^ [ey]	Scroll a row down/up.
z [hl]	Scroll left/right one column.
z [HL]	Scroll left/right half a page.
zm	Horizontally to position the selected cell at the center of the screen.
zz	Vertically to position the selected cell at the middle of the screen.
z [tb]	Vertically to position the selected cell at the top/bottom of the screen.

Visible Navigation

H	Go to the top row visible on screen.
L	Go to the lowest row visible on screen.
M	Go to the middle row on the screen.
g0	Go to the leftmost column visible on screen.
g\$	Go to the rightmost column visible on screen.
gM	Go to the middle column on the screen.

Other commands

^L	Redraw the screen.
Z [rc]	Zap (hide) the current row/column.
S [rc]	If a range is selected, show the rows/columns hidden in the range.
/	Alias for ':int goto '.
n/N	Move to next/previous search match.
rl	Lock the current cell or range.
ru	Unlock a locked cell or range, making it editable.
rv	Valueize the current cell or range.



By **isaacnewton**

Published 1st March, 2021.

Last updated 1st March, 2021.

Page 1 of 1.

Sponsored by **Readable.com**

Measure your website readability!

<https://readable.com>