

Basic

C-x C-c	Quit Emacs
C-g	Abort
C-x C-f	Find a file
C-x C-s	Save the file
C-x s	Save some buffers
C-x C-b	List buffers
<ESC><ESC><ESC>	All-purpose get out

Movement

C-f	Forward one character
C-b	Back one character
C-n	Next line
C-p	Previous line
C-a	Beginning of line
C-e	End of line
M-f	Forward one word
M-b	Back one word
M-e	Next sentence
M-a	Previous sentence
M-v	Previous screen
C-v	Next screen
M-<	Beginning of buffer
M->	End of buffer
M-g g	Jump to specified line
C-l	Redisplay the test around the cursor

Window

C-x k	To close current buffer
C-x 0	To close current window
C-x 1	Remove other windows
C-x 2	New window below
C-x 3	New window on the right
C-x 4 C-f	Find file in other window
C-x o	moves to the other window
C-M-v	Scroll the bottom window
M-x make-frame	: open a new frame
M-x delete-frame	: removes the selected frame.

Repeating

C-u 8 C-f	Move forward 8 character
M-8 C-f	Move forward 8 character
C-u 8 C-v	Scrolls by 8 lines, not screenful
C-u 8 *	insert * 8 times

Most Emacs commands accept a numeric argument, The way you give a command a repeat count is by typing C-u and then the digits before you type the command.

Alternative: type the digits while holding down the META/CTL key

Editing

C- <SPC>	Start selecting text
C-d	Delete the next char
M-DEL	Kill the word before the cursor
M-d	Kill the next word after the cursor
C-k	Kill to end of line
M-k	Kill to the end of the sentence
C-w	Cut selection
M-w	Copy selection
C-/	Undo, C-_ \ C-x u do the same
C-y	Yank
M-y	Yank pop
M-u	End of word to uppercase
M-l	End of word to lowercase

Auto-Fill-Mode

M-x auto-fill-mode	toggles the mode
C-x f	Set the auto fill width
M-q	Re-fill the paragraph

Searching

C-s	Incremental search
C-r	Reverse search
	Back / remove characters
M-%	query before replacing string
C-M-%	query before replacing regexp

Mark ring

C-<SPC> C-<SPC>	Set the mark
C-u C-<SPC>	Pop the mark point

Help

C-h t	Open the tutorial
C-h v	Help for variable
C-h f	Help for function
C-h k	Help for shortcuts
C-h r	Help menu
C-h i	Read included Manuals
C-h b	Display all key bindings

Sr-speed-bar

M-1	Toggle the sr-speed-bar
-----	-------------------------

U to go up parent directory.

n or **p** moves to next or previous node.

M-n or **M-p** moves to next or previous node at the current level.

b switches to buffer list.

f switches back to file list.

Tuareg Mode

C-c C-c	Compile
C-c C-e	Eval phrase
C-x C-e	Eval phrase
C-M-X	Eval phrase
C-c C-r	Eval region
C-c C-b	Eval buffer
M-q	indent phrase
C-c C-s	tuareg-run-caml
C-c C-k	tuareg-kill-caml
C-c C-a	switch between ml/mli



Tuareg Mode (cont)

M-n/p switch last repl input

M-x tuareg-mode: Turn on Tuareg major mode

M-x run-ocaml: Start the OCaml REPL

S-<RET>: Evaluate a phrase

M-x ocamldebug FILE: Run the Ocaml debugger

Merlin Mode

C-c C-l Locate definition

C-c C-SPC Go back

C-c C-n merlin-phrase-next

C-c C-p merlin-phrase-prev

Undo Tree

M-_ Redo

C-x u undo-tree-visualize



By **tacinight**
cheatography.com/tacinight/

Not published yet.
Last updated 21st November, 2018.
Page 2 of 2.

Sponsored by **ApolloPad.com**
Everyone has a novel in them. Finish Yours!
<https://apollopad.com>